

FIGURE 12-27 (a) Ten traces are made across the abdomen by moving the transducer, or by using an array of transducers. (b) The echoes are plotted as dots to produce the image. More closely spaced traces would give a more detailed image.

moved, or an array of transducers is used, each of which sends out a pulse at each position and receives echoes as shown in Fig. 12-27. Each trace can be plotted, spaced appropriately one below the other, to form an image on a display terminal as shown in Fig. 12-27b. Only 10 lines are shown in Fig. 12-27, so the image is crude. More lines give a more precise image.[†] Photographs of ultrasound images are shown in Fig. 12-28.

[†]*Radar* used for aircraft involves a similar pulse-echo technique except that it uses electromagnetic (EM) waves, which, like light, travel with a speed of 3×10^8 m/s.




FIGURE 12-28 (a) Ultrasound image of a human fetus (with head at the left) within the uterus. (b) False-color high-resolution ultrasound image of a fetus. (Different colors represent different intensities of reflected pulses.)

Summary

Sound travels as a longitudinal wave in air and other materials. In air, the speed of sound increases with temperature; at 20°C, it is about 343 m/s.

The **pitch** of a sound is determined by the frequency; the higher the frequency, the higher the pitch.

The **audible range** of frequencies for humans is roughly 20 Hz to 20,000 Hz (1 Hz = 1 cycle per second).

The **loudness** or **intensity** of a sound is related to the amplitude squared of the wave. Because the human ear can detect sound intensities from 10^{-12} W/m² to over 1 W/m², sound levels are specified on a logarithmic scale. The **sound level** β , specified in decibels, is defined in terms of intensity I as

$$\beta = 10 \log \left(\frac{I}{I_0} \right), \quad (12-1)$$

where the reference intensity I_0 is usually taken to be 10^{-12} W/m².

Musical instruments are simple sources of sound in which **standing waves** are produced.

The strings of a stringed instrument may vibrate as a whole with nodes only at the ends; the frequency at which this standing wave occurs is called the **fundamental**. The fundamental frequency corresponds to a wavelength equal to twice the length of the string, $\lambda_1 = 2L$. The string can also vibrate at higher frequencies, called **overtones** or **harmonics**, in which

there are one or more additional nodes. The frequency of each harmonic is a whole-number multiple of the fundamental.

In wind instruments, standing waves are set up in the column of air within the tube.

The vibrating air in an **open tube** (open at both ends) has displacement antinodes at both ends. The fundamental frequency corresponds to a wavelength equal to twice the tube length: $\lambda_1 = 2L$. The harmonics have frequencies that are 1, 2, 3, 4, ... times the fundamental frequency, just as for strings.

For a **closed tube** (closed at one end), the fundamental corresponds to a wavelength four times the length of the tube: $\lambda_1 = 4L$. Only the odd harmonics are present, equal to 1, 3, 5, 7, ... times the fundamental frequency.

Sound waves from different sources can interfere with each other. If two sounds are at slightly different frequencies, **beats** can be heard at a frequency equal to the difference in frequency of the two sources.

The **Doppler effect** refers to the change in pitch of a sound due to the motion either of the source or of the listener. If source and listener are approaching each other, the perceived pitch is higher; if they are moving apart, the perceived pitch is lower.

[*Shock waves and a sonic boom occur when an object moves at a supersonic speed—faster than the speed of sound. Ultrasonic-frequency (higher than 20 kHz) sound waves are used in many applications, including sonar and medical imaging.]